





Motor Jogging

System Configuration



What is Jogging?

- Jogging is the simplest form of closed-loop motor move
- Typically, jogging acts on a single motor
 - Not associated with coordinate systems or motion programs
 - Can be performed for multiple motors at once



- Jogging is ideal for point to point moves (positioning) or indefinite movement in one direction
- Jogging can be performed online or in-programs (with some exceptions)

Basic Online Jog Commands

COMMAND	DESCRIPTION	EXAMPLES	
J/	Decelerate to a stop / put motor in closed loop	#1J/	#1..4J/
J={constant}	Jog to a specified position	#1J=10	#1,2,4J/
J^{constant}	Jog to a specified position relative to the motor's actual position	#1J^-15	#1,4J+
J+	Jog positive indefinitely	#1J+	
J-	Jog negative indefinitely	#1J-	
J=	Jog to “pre-jog” position (most recently programmed position)	#1J=	
J=={constant}	Jog to a specified position, then set that position as the “pre-jog” position	#1J==25	
J=*	Jog to Motor[x].ProgJogPos	#1J=*	



Note

J is the short version with **Sys.NoShortCmds** at default of 0. If it is set to 1, must use the long version **Jog**



Note

Can change jog parameters at any time. New values do not take effect until the next jog command

Basic Program Jog Commands

COMMAND	DESCRIPTION	EXAMPLES	
Jog/	Decelerate to a stop / put motor in closed loop	Jog/1	Jog/1..4
Jog={data}	Jog to a specified position	Jog1=10	Jog/1,2,4
Jog^{data}	Jog to a specified position relative to the motor's actual position	Jog1^-15	Jog+1,4
Jog+	Jog positive indefinitely	Jog+1	
Jog-	Jog negative indefinitely	Jog-1	
Jogret	Jog to "pre-jog" position (most recently programmed position)	Jogret1	
Jogret={data}	Jog to a specified position, then set that position as the "pre-jog" position	Jogret1=25	
Jogret=*	Jog to Motor[x].ProgJogPos	Jogret1=*	



Note

Short version **J** is not used in programs regardless of the **Sys.NoShortCmds** setting



Note

Can change jog parameters at any time. New values do not take effect until the next jog command

Jog Move Profile

➤ A jog move profile is governed by 3 (saved) elements:

- Motor[].JogSpeed (always positive)
- Motor[].JogTa
- Motor[].JogTs

➤ Acceleration/deceleration can be specified by either time OR rate

➤ Units

- JogSpeed [**motor units/msec**]
- JogTa
 - [**msec**] if > 0 , acceleration time
 - [**msec²/motor unit**] if < 0 , inverse acceleration rate
- JogTs
 - [**msec**] if > 0 , s-curve time
 - [**msec³/motor unit**] if < 0 , inverse jerk rate



Note



If **JogTa** is less than 0, **JogTs** must also be set less than 0, so both specify rate

Time Acceleration Settings

- JogTa and JogTs are > 0
- Rate of acceleration will be different for various speeds
- Can be optimized for pre-defined move sizes
- Accel and jerk limits are not known/critical
 - Set by “look and feel”


➤ Time accel. rules

- If $\text{JogTa} \geq \text{JogTs}$
 - Total Accel. Time = $\text{JogTa} + (\frac{1}{2} \text{JogTs} + \frac{1}{2} \text{JogTs})$
= $\text{JogTa} + \text{JogTs}$
- If $\text{JogTa} < \text{JogTs}$
 - Total Accel. Time (extended) to = $2 * \text{JogTs}$



Rate Acceleration Settings

- JogTa and JogTs are < 0
- Provides more seamless blending into newly commanded moves
- Rate of acceleration same for various speeds
 - Optimized move times
- Known, or desired acceleration and jerk limits



- E.g. For a linear motor set up in mm:

- $$\text{JogTa} = -1000 / (\text{Gs} * 9.806)$$
- $$\text{JogTs} = -1000000 / (\text{GsPerS} * 9.806)$$

- Where:
 - Gs is desired acceleration in G gravity (or m/s^2)
 - GsPerS is desired jerk in Gs per second (or m/s^3)

- E.g. For a rotary motor set up in degrees:

- $$\text{JogTa} = -1000 / (\text{DegPerS2})$$
- $$\text{JogTs} = -1000000 / (\text{DegPerS3})$$

- Where:
 - DegPerS2 is desired acceleration rate in degrees per s^2
 - DegPerS3 is desired jerk rate in degrees per s^3



Jogging Quiz

➤ For these time acceleration settings

- JogTa = 150, JogTs = 0, JogSpeed = 0.100
- JogTa = 50, JogTs = 75, JogSpeed = 0.200
- JogTa = 125, JogTs = 25, JogSpeed = 0.300

- What is the total acceleration time in each case?
- Does JogSpeed matter?

- If $\text{JogTa} \geq \text{JogTs}$
 - Total Accel. Time = $\text{JogTa} + (\frac{1}{2} \text{JogTs} + \frac{1}{2} \text{JogTs})$
= $\text{JogTa} + \text{JogTs}$
- If $\text{JogTa} < \text{JogTs}$
 - Total Accel. Time (extended) to = $2 * \text{JogTs}$



Jogging Quiz

➤ For a linear actuator set up in motor units of millimeters

- If $\text{JogTa} = -67.985588 \text{ [ms}^2/\text{mm]}$
 - What is the maximum acceleration in Gs?

- If $\text{JogTs} = -463.53809 \text{ [ms}^3/\text{mm]}$
 - What is the maximum jerk in Gs/s?

- Note:
 - $1\text{G} = 9.806 \text{ m/s}^2$

$$\text{JogTa} = -1000 / (\text{Gs} * 9.806)$$

$$\text{JogTs} = -1000000 / (\text{GsPerS} * 9.806)$$



Note

In a track test, the Ferrari LaFerrari launches off the line with a jerk rate of about 700 Gs/s

Plot Tool

➤ Rename (optional)

- Cmd position [mu]
- Following error [mu]
- Cmd velocity [mu/s]
- Cmd Acceleration [Gs]

- Motor[1].Desired.Jerk
 - Jerk Limit [Gs/s]
- Motor[1].InPos

➤ Scale Factors for #1

- Accel in Gs:
 - $= 1 / (9.806 * 1000)$
- Jerk in Gs/s:
 - $= 6 * 1000000 / 9.806$

Plot : Online[192.168.0.201:SSH]

File View Gather Options

Selected Preset: Jogging Exercise

Step 1 - Possible Data Sources

Quick Detailed Manual

Motor1 Motor2 Motor3 Motor4

Gather Settings

Sampling Settings

Phase Servo

Gather duration (ms): 50001.95

Max Gather Samples: 100000

Sample Period: 1

Step 2 - Data To Sample

Time(sec) Motor[1].ActPos Motor[1].DesPos Motor[1].JogCmd Motor[1].Desired.Jerk Motor[1].InPos

Step 3 - Data Processing

Time(sec) MTR1 POSITION mu MTR1 VELOCITY mu/sec MTR1 ACCELERATION Gs MTR1 FOLLOWING ERROR MTR1 JERK LIMIT Gs/sec MTR1 INPOS BIT

Scale Factor = 1.0197838058

Offset = 0

Function = (d2/dt) Motor[1].DesPos.a

Step 4 - Plotting

Left Axis: MTR1 VELOCITY mu/sec

Right Axis: MTR1 FOLLOWING ERROR

Horizontal Axis: Time(sec)

1 Gather Data

2 Upload Data

3 Plot Data

Process Data

Scale and Offset

Scale Factor: 1.0197838058

Offset: 0

Data Processing

Function Name F(x) = MTR1 ACCELERATION Gs

Process = Scale Factor * ((d2/dt) Motor[1].DesPos.a) + Offset

Available Process: Add(+) Add

Available Items: Time(sec) Add

Insert Update Cancel

Jogging Exercise

➤ Motor #1 is set up in motor units of millimeters

- What should JogSpeed be set for a setting of 200 mm/s?
- Find the shortest acceleration time using JogTa and JogTs so that for any jog move the following error does not exceed 50 μm (0.050 mm)
 - Following error limit is set to 500 μm (Motor[1].FatalFeLimit = 0.500)
 - Use the plot tool to display the following error during move(s)
- Test for jog direction reversal at top speed!
- What is the observed maximum commanded acceleration in Gs? – plot

Terminal: Online [192.168.0.201 : SSH]

```
Gather.Enable = 0  
Gather.Enable = 2 #1J+  
#1J-  
Gather.Enable = 0 #1J/
```



Abort Deceleration

Abort Deceleration

➤ Uses Motor[].AbortTa, and Motor[].AbortTs

➤ Automatically triggered

- Exceeds a hardware over-travel limit
- Exceeds a software over-travel limit
- Coordinate system ABORT commanded
- Coordinate system run-time error

➤ Same “deceleration” profile and rules as jogging

➤ Axis/machine specific

- Typically, configured to allow stopping from top speed without:
 - Violating the hardware limits
 - Excessive jerk or vibration
 - Exceeding the following error limit

➤ Units (same rules as JogTa, and JogTs)

- AbortTa
 - [msec] if > 0 , acceleration time
 - [msec²/motor unit] if < 0 , inverse acceleration rate
- AbortTs
 - [msec] if > 0 , s-curve time
 - [msec³/motor unit] if < 0 , inverse jerk rate



Note

If **AbortTs** is less than 0, **AbortTa** must also be set less than 0, so both specify rate



Note

Certain axes may be oversized and physically incapable of stopping within the hardware limits at top speeds. In these cases, software limits (**MinPos** and **MaxPos**) are configured with an extended abort deceleration time (or lower rate)

Abort Deceleration Exercise

➤ Your linear motor (#1) has a maximum speed of 250 mm/s

- Find the shortest decel. time using AbortTa or AbortTs so that aborting from top speed the following error does not exceed 100 μm (0.100 mm)
 - Following error limit is set to 500 μm (Motor[1].FatalFeLimit = 0.500)
 - Abort using one of the hardware over-travel limits
 - Use the plot tool to display the following error during deceleration
- Test in both directions!
- What is the observed maximum commanded acceleration in Gs? – plot



Can you use the ABORT command instead of the hardware over-travel limit to abort

Note

```
Terminal: Online [192.168.0.201 : SSH]
Gather.Enable = 0
Gather.Enable = 2 #1J+
&*abort
Gather.Enable = 0
```